
# **Video Recording**

#### **Video Recording**

Introduction to the results of routine experiments
Code Explanation
Code structure

## Introduction to the results of routine experiments

In this section, we will learn how to use the camera on K230 to record video.



The example code for this section is located in: [Source Code/10.Media/04.record\_video.py]

We use CanMV IDE to open the sample code and connect K230 to the computer via USB.


Click the Run button in the lower left corner of CanMV IDE, K230 will start recording 500 frames of video, and the recording results will be saved as

【/data/video/test.mp4】 (You can also modify it yourself)

Note 1: If the built-in player of Windows cannot open the recorded video normally, you can use a third-party player with better compatibility such as VLC Player or PotPlayer, or use the code in the next section [Video Playback] tutorial to watch the video in the frame buffer of CanMV IDE

Note 2: During recording, the K230 screen will not display anything.

2025.2 Revision: The video player included in CanMV IDE can open the recorded video normally. It is recommended to use this



### **Code Explanation**

#### **Code structure**

- This example implements an MP4 recording class based on K230
  - 1. The overall structure of the class
  - MP4Recorder The class is the core class and contains the following main methods:
    - \_\_init\_\_: Initialization method
    - start\_recording: Start recording
    - stop\_recording: Stop recording
    - \_\_de1\_\_\_: Destructor
  - 2. Key Attribute Management

```
def __init__(self, width=640, height=480, max_record_time=10):
    self.width = width
    self.height = height
    self.max_record_time = max_record_time
    self.mp4_muxer = None
    self.frame_count = 0
```

- Manage video parameters (width, height)
- Control recording duration
- Maintaining MP4 muxer instances
- Keep track of the number of frames processed
- 3. Recording process control

```
def start_recording(self, file_path):
    # 初始化阶段
    # init
    self.mp4_muxer = Mp4Container()
    mp4_cfg = Mp4CfgStr(self.mp4_muxer.MP4_CONFIG_TYPE_MUXER)

# 录制循环 recode loop
while True:
    self.mp4_muxer.Process()
    # 时长检查和退出控制 check time and exit
```

- Use try-finally to ensure resource release
- Implementing \_\_de1\_\_ destructors as a fallback cleanup mechanism
- stop\_recording Method handles resource release
- 5. Error handling

```
try:
    # 录制逻辑
    # ... recording ...
except BaseException as e:
    print(f"录制过程出错 Recording error: {e}")
finally:
    self.stop_recording()
```

6. Example Usage

```
def main():
    recorder = MP4Recorder(width=640, height=480, max_record_time=10)
    recorder.start_recording("/data/video/test.mp4")
```