

Training using the online platform

Training using the online platform

Introduction

1. Prepare training data
2. Train the model on the training platform
3. Use the code and model we downloaded

The following is the latest version of the tutorial on 2025.06.10

The following is an old version tutorial, which is only used for reference and backup.

4. Effect Optimization

Introduction

In this section, we will introduce the online cloud platform provided by CanMV for model training. We take the commonly used detection model as an example to let K230 recognize two items, my bracelet and screwdriver


1. Prepare training data

We use the routine code in the [2.Basic Tutorial - 19.Camera] section to take pictures. For specific operations, please refer to the tutorial in the [2.Basic Tutorial - 19.Camera] section


2. Train the model on the training platform

Online training platform address: <https://www.kendryte.com/en/training/dataset>



Click the Register button




Fill in your personal information and click Register




After successful registration, you will be automatically logged in. We click "Create training set"




Click Edit



Click to upload image



After uploading the picture, we click the Annotate button



1. We first select the label box, enter a label name, and then press Enter.
2. Then we can use the mouse to mark the object to be detected on the picture.
- 3.

文档教程 →

← 1 / 46

Screwdriver × + new tag


Start

Dataset

Records

Annotation steps: Select the tag and the cursor will show '+' on the image

Deleting or modifying a callout step: Exit the annotation state and select a annotation box to delete or modify it



Exit the annotation state Delete Annotation

All (46) | Labeled (0) | Unlabeled (46)

1	1.jpg	Screwdriver
2	1_C.jpg	
3	3.jpg	
4	3_A.jpg	
5	3_C.jpg	
6	4.jpg	
7	4_G.jpg	
8	4_W.jpg	
9	5_I.jpg	
10	5.jpg	

< 1 2 3 4 5 >

文档教程 →

← 27 / 46

Screwdriver × Band + new tag


Start

Dataset

Records

Annotation steps: Select the tag and the cursor will show '+' on the image

Deleting or modifying a callout step: Exit the annotation state and select a annotation box to delete or modify it



Exit the annotation state Delete Annotation

All (46) | Labeled (46) | Unlabeled (0)

1	10.jpg	Screwdriver
2	11.jpg	Screwdriver
3	12.jpg	Screwdriver
4	6_X.jpg	Screwdriver
5	1.jpg	Band
6	2.jpg	Band
7	3.jpg	Band
8	6.jpg	Band
9	4.jpg	Band
10	10.jpg	Band

< 1 2 3 4 5 >

After all the markings are completed, we click the return button

文档教程 →

46 / 46

Screwdriver ×

Band

+ new tag

Exit the annotation state

Delete Annotation

All (46) | Labeled (46) | Unlabeled (0)

1 17.jpg Band

2 18.jpg Band

3 21.jpg Band

4 19.jpg Band

5 20.jpg Band

6 22.jpg Band

< 1 2 3 4 5 >


Start

Dataset

Records

Annotation steps: Select the tag and the cursor will show '+' on the image

Deleting or modifying a callout step: Exit the annotation state and select a annotation box to delete or modify it



We click the training button

文档教程 →

Start

Dataset

Records

Image Detection

Total Images 46

Upload Images

Upload Archive

Annotate


Train

Archive Format Description


Tags All No Tag Screwdriver Band

	Name	Tag	Actions
1	1.jpg	Screwdriver	Delete
2	1_C.jpg	Screwdriver	Delete
3	3.jpg	Screwdriver	Delete
4	3_A.jpg	Screwdriver	Delete
5	3_C.jpg	Screwdriver	Delete
6	4.jpg	Screwdriver	Delete
7	4_G.jpg	Screwdriver	Delete
8	4_W.jpg	Screwdriver	Delete
9	5_I.jpg	Screwdriver	Delete
10	5.jpg	Screwdriver	Delete


< 1 2 3 4 5 >




Fill in the content as shown in the picture and click OK




Waiting for training (need to queue if there are many people)



The training takes a long time and it is uncertain how long it will take. Closing the webpage or turning off the computer will not affect the training. You can do other things first.



After waiting for the training to end, the interface is as follows



We return to the place before starting training, find the training record, and click Download

文档教程 →

Start

Dataset

Records

Training Record

Tip: 1. After the training is completed, the model will be automatically sent to the registered email.

2. Each user supports only one training task running at the same time.

3. The maximum training duration for a single task is 24 hours. If it exceeds the time, the task will be terminated early according to the server resource situation.

4. The training duration is strongly related to the number of files and training iterations of your dataset. If the training time is too long, consider reducing the corresponding quantity.

ID	Name	Dataset	Type	Chip	Status	Update Time	Operation
20056	Test Bands and Screwdrivers	yahboom_test	Image Detection	k230	✓ Completed	2025-05-13 1...	<div>Detail</div> <div>Download</div> <div>Delete</div>

3. Use the code and model we downloaded

The following is the latest version of the tutorial on 2025.06.10


Note: If you are using firmware 1.3.3 or earlier, please update to the latest version. The latest version of the firmware can be downloaded from our official website tutorial page

The downloaded compressed package is as follows

det_results	文件夹				
mp_deployment_source	文件夹				
README.pdf	149.0 KB	149.0 KB	WPS PDF 文档		2025-06-24 16:29

The [det_results] directory contains the results of our test verification, we can open it and take a look.

Here are the results of the verification test. If the object in the picture is correctly framed, then basically there is no big problem with the trained model




Then we open the [mp_deployment_source] folder, which contains our model file and configuration file

K230_New_det.zip\mp_deployment_source - 解包大小为 7.4 MB					搜索包内文件
名称	压缩前	压缩后	类型	修改日期	
.. (上级目录)			文件夹		
best_AnchorBaseDet_can2_5_s_20250624162548.kmodel	7.2 MB	7.2 MB	KMODEL 文件	2025-06-24 16:29	
deploy_config.json	1 KB	1 KB	JSON 源文件	2025-06-24 16:29	

Then we return to the sdcard directory of CanMV and create a new folder named [mp_deployment_source]

Put this in the compressed package Unzip the two files to this folder (first unzip to your computer, then copy to the mp_deployment_source folder)



Then open the example source code summary [13.training/deploy_det_video.py]

Change display_mode to "lcd"

```
21
22
23 import os, gc
24 from libs.PlatTasks import DetectionApp
25 from libs.PipeLine import PipeLine
26 from libs.Utills import *
27
28 # Set display mode: options are 'hdmi', 'lcd', 'lt9611', 'st7701', 'hx8399'
29 # 'lt9611' (1920x1080); 'lcd' defaults to 'st7701' (800x480)
30
31 display_mode = "lcd"
32
33 # Define the input size for the RGB888P video frames
34 rgb888p_size = [1280, 720]
35
36 # Set root directory path for model and config
37 root_path = "/sdcard/mp_deployment_source/"
38
39 # Load deployment configuration
40 deploy_conf = read_json(root_path + "/deploy_config.json")
41 kmodel_path = root_path + deploy_conf["kmodel_path"] # KModel path
42 labels = deploy_conf["categories"] # Label list
43 confidence_threshold = deploy_conf["confidence_threshold"] # Confidence threshold
44 nms_threshold = deploy_conf["nms_threshold"] # NMS threshold
45 model_input_size = deploy_conf["img_size"] # Model input size
46 nms_option = deploy_conf["nms_option"] # NMS strategy
47 model_type = deploy_conf["model_type"] # Detection model type
48 anchors = []
49 if model_type == "AnchorBaseDet":
50     anchors = deploy_conf["anchors"][0] + deploy_conf["anchors"][1] + deploy_conf["anchors"][2]
51
52 # Inference configuration
53 inference_mode = "video" # Inference mode: 'video'
54 debug_mode = 0 # Debug mode flag
55
56 # Create and initialize the video/display pipeline
57 nl = Pipeline(rgb888p_size=rgb888p_size, display_mode=display_mode)
```

After the modification, click the run button in the lower left corner of the IDE to see the effect of the case running.

Note: After testing, the new version of the tutorial may drop frames after deployment. At this time, you can try to use the old version of the tutorial to deploy.

The det_video.py file required by the old version of the tutorial has been placed in [Source Code Summary / 13.training / det_video.py]

The following is an old version tutorial, which is only used for reference and backup.


The downloaded file is a compressed file with the following contents

Test Bands and Screwdrivers.zip - ZIP 压缩文件, 解包大小为 64,778,111 字节					
名称	大小	压缩后大小	类型	修改时间	CI
..			File folder		
det_results	126,479	126,479	File folder		
cpp_deployment_source.zip	58,384,570	58,384,570	WinRAR ZIP 压缩...	2/25/2025 7:38 ...	4C
mp_deployment_source.zip	6,257,196	6,257,196	WinRAR ZIP 压缩...	2/25/2025 7:38 ...	7F
README.md	9,866	9,866	Markdown File	2/25/2025 7:38 ...	3E

We can first look at the det_results folder, which contains the results of the verification test. If the objects in the picture are correctly framed, then basically there is no big problem with the trained model.

Next, we unzip mp_deployment_source and create a mp_deployment_source folder in the /sdcard/ directory of K230, and put the unzipped contents into it.

(Mainly put the model file ending with .kmodel and the configuration file ending with .json in it. The remaining two py files are used for running and can be left out)



Then we open CanMV IDE, copy the code of det_video.py and run it, and we can see that K230 can detect the objects we just marked.

Here we need to make some modifications to det_video.py:

The original code is as follows:

```
display_mode="hdmi"  
if display_mode=="lcd":  
    DISPLAY_WIDTH = ALIGN_UP(800, 16)  
    DISPLAY_HEIGHT = 480  
else:  
    DISPLAY_WIDTH = ALIGN_UP(1920, 16)  
    DISPLAY_HEIGHT = 1080  
  
OUT_RGB888P_WIDTH = ALIGN_UP(1280, 16)  
OUT_RGB888P_HEIGH = 720
```

Modified to:

```
display_mode="lcd"  
if display_mode=="lcd":  
    DISPLAY_WIDTH = ALIGN_UP(640, 16)  
    DISPLAY_HEIGHT = 480  
else:  
    DISPLAY_WIDTH = ALIGN_UP(1920, 16)  
    DISPLAY_HEIGHT = 1080  
  
OUT_RGB888P_WIDTH = ALIGN_UP(1280, 16)  
OUT_RGB888P_HEIGH = 720
```



4. Effect Optimization

At this time, we find that there are too many overlapping frames, so we can try to reduce the nms threshold in deploy_config, so that there will be fewer duplicate frames.

```
{} deploy_config[1].json X
C: > Users > Administrator > AppData > Local > Microsoft > Windows > INetCache > IE > PZ9UWQH3 > {} deploy_config[1].json
1  {
2    "chip_type": "k230",
3    "inference_width": 640,
4    "inference_height": 640,
5    "confidence_threshold": 0.25,
6    "nms_threshold": 0.4,
7    "mncase_version": "2.9.0",
8    "model_type": "AnchorBaseDet",
9    "img_size": [
10     640,
11     640
12   ],
13   "anchors": [
14     [
15       191,
16       151,
17       255,
18       169,
19       239,
```

The default is 0.6, which causes duplicate boxes to appear.

