Color Block Recognition - Color Image

Color Block Recognition - Color Image

Example Results

Code Explanation

Importing Modules

Setting the image size

Initialize the camera (RGB888 mode)

Initialize the display module

Initialize the media manager and start the camera

Set color blob detection parameters

Image Processing and Color Block Detection

Resource release


Parameter adjustment instructions

Example Results

Run this section's example code [Source Code/06.cv_lite/2.rgb888_find_blobs.py]

This section is based on color block recognition for RGB888 (color) images. The K230 will detect blocks in the image that meet the set threshold and mark them with a rectangular box.

Observe the frame rate output on the serial terminal. When the power supply is stable, the frame rate can be stable at around 55 frames.



Code Explanation

Importing Modules

```
import time, os, sys, gc
from machine import Pin
from media.sensor import * # Import the camera interface
from media.display import * # Import the display interface
from media.media import * # Import the media manager
import _thread
import cv_lite # cv_lite extension module
import ulab.numpy as np # MicroPython NumPy library
```

These modules provide the necessary functionality for camera control, image display, memory management, and color block detection.

Setting the image size

```
image_shape = [480, 640] # Height x Width
```

Define the image resolution to 480x640 (height x width). The camera and display modules will be initialized based on this size.

Initialize the camera (RGB888 mode)

```
sensor = Sensor(id=2, fps = 90)
sensor.reset()
sensor.set_framesize(width=image_shape[1], height=image_shape[0])
sensor.set_pixformat(Sensor.RGB888) # RGB888 format / rgb888 format
```

- Initialize the camera and set the frame rate to 90 FPS.
- Use the default camera resolution.
- Resize the output frame to 640x480 and set it to RGB888 format (three-channel color image, suitable for color detection).

Initialize the display module

```
Display.init(Display.ST7701, width=image_shape[1], height=image_shape[0],
to_ide=True, quality=50)
```

Initialize the display module, using the LCD driver chip with a resolution consistent with the image size. to_ide=True indicates that the image will be simultaneously transmitted to the IDE for virtual display, and quality=50 sets the image transmission quality.

Initialize the media manager and start the camera

```
MediaManager.init()
sensor.run()
```

Initialize the media resource manager and start the camera to capture the image stream.

Set color blob detection parameters

```
threshold = [120, 255, 0, 50, 0, 50] # Format: [Rmin, Rmax, Gmin, Gmax, Bmin,
Bmax]
min_area = 100 # Minimum blob area
kernel_size = 1 # Kernel size for morphological ops (used for preprocessing)
clock = time.clock() # Start FPS timer
```

- threshold: Color detection threshold range, in the format [Rmin, Rmax, Gmin, Gmax, Bmin, Bmax], representing the value range of the three RGB channels. Here, detection is set to red (R channel range is 120-255, G and B channels range is 0-50).
- min_area: The minimum area of a connected component. Areas smaller than this value are ignored.
- kernel_size: The kernel size for image erosion and dilation operations, used for preprocessing images to remove noise.
- clock: Used for calculating frame rate.

Image Processing and Color Block Detection

```
while True:
   clock.tick()
   # Capture a frame
   img = sensor.snapshot()
   img_np = img.to_numpy_ref() # Get a reference to the RGB888 ndarray
    # Call the cv_lite extension for color block detection, returning a list of
[x, y, w, h, ...]
    blobs = cv_lite.rgb888_find_blobs(image_shape, img_np, threshold, min_area,
kernel_size)
    # Iterate over the detected color blocks and draw rectangular boxes
    for i in range(len(blobs) // 4): # Correct for integer division
        x = blobs[4*i]
       y = blobs[4*i + 1]
        w = blobs[4*i + 2]
        h = blobs[4*i + 3]
        img.draw_rectangle(x, y, w, h, color=(255, 0, 0), thickness=2) # Red
frame
    # Display the resulting image / Show image with blobs
   Display.show_image(img)
    # Print FPS
    print("finddblobs:", clock.fps())
    # Garbage collection
    gc.collect()
```

- **Image capture**: Use <code>sensor.snapshot()</code> to obtain a frame of image and convert it to a NumPy array reference using <code>to_numpy_ref()</code>.
- **Color block detection**: Call <code>cv_lite.rgb888_find_blobs()</code> to detect color blocks and return a list of detected area information (each blob occupies 4 elements: <code>[x, y, w, h]</code>, i.e., the coordinates of the upper left corner and the width and height).

- Draw rectangle: Traverse each detected blob and draw a red rectangle (color=(255, 0, 0)) on the image to mark the target area.
- **Display image**: Display the processed image to the screen or IDE virtual window.
- **Memory management and frame rate output**: Call <code>gc.collect()</code> to clean up the memory and print the current frame rate through <code>clock.fps()</code>.

Resource release

```
sensor.stop()
Display.deinit()
os.exitpoint(os.EXITPOINT_ENABLE_SLEEP)
time.sleep_ms(100)
MediaManager.deinit()
```

When the program exits, stop the camera, release the display module resources, and clean up the media manager.

Parameter adjustment instructions

- **threshold**: Adjust the threshold range of the RGB channel according to the target color. For example:
 - Detecting red: [120, 255, 0, 50, 0, 50] (R high, G and B low).
 - Detecting green: [0, 50, 120, 255, 0, 50] (G high, R and B low).
 - o Detecting blue: [0, 50, 0, 50, 120, 255] (B high, R and G low).
- min_area: Adjust this value based on the object size. Smaller values detect more small areas, while larger values filter out noise.
- **kernel_size**: Used for image erosion and dilation. Larger values produce stronger noise reduction, but may lose detail in small objects.